B\$SMP – Attach Extended SMEM Substituted Channel

The B\$SMP attaches a substituted Extended SMEM access channel to the original access channel.

1. Invocation

To attach the substituted channel code:

CALL B\$SMP USING original_channel substituted_channel

2. STOP Codes and Exception Conditions

No STOP codes are generated by B\$SMP.

No EXIT codes are generated by B\$SMP.

3. Programming Notes

The B\$SMP can only be used Extended SMEM. Substituted channels may not be used with standard SMEM.

B\$SMP must be called before the extended SMEM substituted channel is used, to attach the substituted channel to the data pages of the original channel. B\$SMP must not be called before the first WRITE operation using the original channel because this operation establishes the data pages for the original channel. The substituted channel must be detached using the B\$CSMP routine before the frame is unloaded otherwise unpredictable program checks will occur when Speedbase attempts to unload the frame.

4. Examples

FRAME TEST ACCESS AA ACCESS AA SUBSTITUTING "AB" DATA DIVISION 77 Z-C4 PIC 9(4) COMP * Count WINDOW W1 USING AA * Display original channel BASE AT 02 03 SCROLL 10 BY 1 SEL AUTOPGE 02 02 "Using AA" A12 02 02 AAFIELD1 ENDWINDOW WINDOW W2 USING AB * Display substituted channel BASE AT 02 03 SCROLL 10 BY 1 SEL AUTOPGE 02 02 "Using AB" A12 02 02 ABFIELD1 ENDWINDOW ENDWINDOW PROCEDURE DIVISION CALL B\$SMDE USING \$AA * Clear record area DO FOR Z-C4 = 1 TO 100 * Write records MOVE Z-C4 TO AAFIELD1 WRITE AA ENDDO * Display original records ENTER WINDOW W1 IGNORE EXCEPTION CLEAR WINDOW W1

CALL B\$SMP USING	G \$AA \$AB	* Attac	h substituted channel
IGNORE EXCEPTION	Ā		
ENTER WINDOW W2		* Displ	ay records via
IGNORE EXCEPTION	A	* subst	ituted channel
CLEAR WINDOW W2			
CALL B\$CSMP USIN	NG \$AB	* Clear	substituted channel
EXIT			
ENDFRAME			

Copy-Books 5.

No copy books required.

6. See Also

ENDSOURCE

B\$CSMP Clear Extended SMEM substituted channel Extended SMEM