

GXDCF\$ - Disable Clearing Field on GX

The GXDCF\$ routine is used to disable the automatic clearing of a field in a window that is already displayed. This routine is typically used to prevent a field with a TXT option displayed in a different attribute from being automatically cleared in ENQ mode.

1. Invocation

To disable the automatic clearing of a field in a window that is already displayed code.

```
CALL GXDCF$ USING window field_name
```

where *window* is the Window Definition of the target window; and *field_name* is the PIC X(6) field name.

2. STOP Codes and Exception Conditions

The following STOP codes may be generated by GXDCF\$:

STOP code	Description
15214	GXDCF\$ has been called by an application that is not running on GX.
15215	Reserved for future use
15216	Field symbols are not available for the window specified
15217	The field specified is not present in the window
15218	An attempt was made to call GXDCF\$ on an incompatible version of GX. The version of GX must be V2.6, or later.
15219	The specified window is not currently displayed on GX
15220	The specified field could not be found by GX

No exception conditions are returned by GXDCF\$.

3. Programming Notes

GXDCF\$ is only available when running on GX. Any attempt to use GXDCF\$ on a non-GX terminal will result in a STOP code.

The target field must be specified as a PIC X(6) field rather than as a direct symbol. For example, the following use of GXDCF\$ is **incorrect** and will almost certainly result in a STOP 15217:

```
CALL GXDCF$ USING W1 W1NAME
```

The following example demonstrates the **correct** use of GXDCF\$:

```
CALL GXDCF$ USING W1 "W1NAME"
```

Note that only the first occurrence of a multiply-occurring field within a window can be specified.

4. Examples

[EXAMPLE REQUIRED]

5. Copy-Books

None.

6. See Also

None.