

# FMESS\$ - Return Formatted Windows Error Message

The FMESS\$ routine can be used to convert a Windows error number into a formatted, verbose error message.

## 1. Invocation

To convert a Windows error number into a formatted message code:

```
CALL FMESS$ USING number length area
```

where *number* is a PIC 9(9) COMP field containing the Windows error number (normally returned in the \$\$CRES System Variable); *area* is a PIC X(n) data area to hold the returned error message and *length* is a PIC 9(4) COMP field containing the size of the data area.

## 2. STOP Codes and Exception Conditions

No STOP codes are generated by FMESS\$.

The following exception conditions may be returned by FMESS\$:

EXIT code	\$\$COND	Description
10501	01	Windows returned an error condition when attempting to format the error code.

## 3. Programming Notes

FMESS\$ is normally used to obtain a descriptive error message from a numeric Windows error code returned in the \$\$CRES System Variable by a variety of sub-routines; or in the DSRES32 field by an SVC-61 call. FMESS\$ is only supported on GSM (Windows) configurations. The message area is set to SPACES if FMESS\$ is used on a GSM (Unix) configuration.

**Important Note:** The length parameter is updated by the routine to return the **actual length** of the text message returned. Consequently, this field must be a data-item (i.e. not a literal) and must be reset to the actual length of the data-area each time FMESS\$ is called by an application. For example:

```
DATA DIVISION
77 X-100 PIC X(100)
PROCEDURE DIVISION
CALL FMESS$ USING $$CRES 100 X-100 * Wrong. Self-modifying code !!!
```

```
DATA DIVISION
77 X-100 PIC X(100)
77 Z-LENG PIC 9(4) COMP
VALUE 100
PROCEDURE DIVISION
CALL FMESS$ USING $$CRES Z-LENG X-100 * Wrong. Z-LENG is altered
```

```
DATA DIVISION
77 X-100 PIC X(100)
77 Z-LENG PIC 9(4) COMP
PROCEDURE DIVISION
MOVE 100 to Z-LENG
CALL FMESS$ USING $$CRES Z-LENG X-100 * Correct
```

## 4. Examples

None.

## 5. Copy-Books

None.

## 6. See Also

FMES0\$ Return Formatted Windows Error Message